


General Settings

162 Gurjeet Kaur March 30, 2019 Manage Settings

6846 0

Tools section contains a list of various configuration settings related to your knowledge base. To manage these settings expand "Tools" section of the left navigation bar and click on "Manage Settings" as shown below:



Manage Settings is further divided into different subsections to categorize the settings properly. By default, the **General Settings** page is displayed which is further categorized into four parts:

1. General Settings
2. IP Address Restriction Settings
3. Product Details
4. Mail Server Settings
5. Database Settings

GENERAL SETTINGS SAVE

Down for Maintenance?

☐ Yes

Knowledge Base Name

Support Knowledge Base

Knowledge Base URL

http://www.knowledgebase-script.com/kb

KB Access

☐ Restricted

☒ Unrestricted

Down for Maintenance?: If checked, it will display down for maintenance page to front end users instead of knowledge base details. You can enable this setting during system enhancement or troubleshooting and can disable it after the enhancement period to bring back the actual knowledge base.

Knowledge Base Name: Enter name of the knowledge base in this field. This name will be displayed in the header section of the front end.

Knowledge Base URL: This is the URL where the knowledge base is installed. However, please note knowledge base wouldn't work properly if the URL is incorrect.

KB Access: If radio button **Restricted** is checked, then front-end users must log in first in order to access the Knowledge Base. In case **Unrestricted**, front-end users would be able to access the knowledge base even if they are not logged in.

IP ADDRESS RESTRICTION SETTINGS SAVE

Enable Restriction? ☒ Yes

Restriction Type

☒ Allowed IPs
 ☐ Blocked IPs

IP Address List

192.168.1.23

(Separated by commas. For example: 192.168.1.20, 77.65.11.21, 178.71.98.90, ... and so on)

Enable Restriction: You can enable this option to control the restriction of specified IP addresses (mentioned in IP Address list).

Restriction Type: If radio button **Allowed IPs** is checked, then users with IP addresses specified in IP Address list would be able to access the knowledge base. Whereas if **Blocked IPs** is checked, then the users with IP addresses mentioned in below list would be blocked and won't be able to access the knowledge base.

IP Address List: Specify the IP Addresses according to which you want to allow or block the users to access the knowledge base. Please note that you can mention multiple IP addresses separated by a comma (,).

This feature is available only in enterprise edition of PHPKB Software.

PRODUCT DETAILS

Software Version

PHPKB 8.0 Standard Edition (Installed on: Jun 1, 2015)

SAVE

Admin Users

5 (Upgrade License) | [Enter Upgrade License Key](#)

Support & Maintenance

Expired on Aug 5, 2012 - [Extend Support Subscription](#) | [Enter Extended Support License](#)

Software Version: This field displays version (Standard/Enterprise/Standard ML/Enterprise ML) of PHPKB knowledge base software installed on your server along with installation date.

Admin Users: This field displays the admin users license purchased by you. If you have upgraded the admin user license, you should enter your new license key in software by using the link; **Enter Upgrade License Key**.

Support & Maintenance: This field displays a date after which your support and maintenance period will expire. You can purchase extended support by clicking on **Extend Support Subscription** link. It would send an email to the sales department for extending support period.

MAIL SERVER SETTINGS

Outgoing Mail Server

☒ Use Default SMTP Server
 ☐ I will not configure SMTP Server

SAVE

Debug Mode?

Off

Debug Output

error_log

Send Mails From

Enter email address...

Email Address

Enter email address

Send Test Email

Outgoing Mail Server: This field controls the email server used for PHPKB knowledge base. **Default SMTP Server** allows PHPKB Software to use the internal PHP mail function to send emails. Click on **I will not configure SMTP server** to specify the details of your own SMTP server. Fill the details of SMTP settings in different fields provided (Refer figure below).

Outgoing Mail Server

• Don't use Default SMTP Server

✓ Let me configure SMTP Server

SMTP Hostname SAVE

SMTP Username

SMTP Password

SMTP Port

Authentication? ☐ Yes, use authentication

SMTP Hostname - Enter either the fully qualified domain name (e.g. mail.domain.com) or the IP address (e.g. 192.168.0.1) of your SMTP server.

SMTP Username - If your SMTP server requires authentication, then you need to provide the login username in order to connect to the SMTP server and send the emails.

SMTP Password - For the authentication, you need to provide the login password in order to connect to the SMTP server and send the emails.

SMTP Port - You need to specify the port number on which your SMTP server is listing. The default port number is 25.

Authentication? - If your server requires authentication then enable this option (See figure below).

Authentication? ☒ Yes, use authentication SAVE

Encryption Method None

Debug Mode? None

Debug Output TLS

Encryption Method - It is used to provide communication security over a computer network. You can select **None** option to ignore the encryption. **Secure Sockets Layer** (SSL) is a protocol for securing connections between network application clients and servers over an insecure network such as the internet whereas **Transport Layer Security** (TLS) provides privacy and data integrity between two communicating computer applications.

Debug Mode: It is a troubleshooting environment in which you can track down the error by turning it on. It is advised to turn this setting **On** only when you experience any issues with your SMTP server otherwise keep it turned **Off**.

Debug Output: Select a suitable debug output in this field. **Error_log** will push all errors into an error-log file of your web server.

Echo option will display error immediately as they occur and **Return** will neither save errors into an error-log file nor display them.

Send Mails From: Enter an email address in this field which will be used to send all outgoing emails.

Email Address: Enter an email address in this field on which you want to receive test email from the system.

MySQL Database Settings -

